

## PATTERN 7735

### PATTERN PIECES:

A B	1	Center Front 2x	B	17	Cuff 2x
A B C	2	Side Front 2x	B	18	Zipper Underlay 2x
A B C	3	Center Back 1x	B	19	Belt 2x
A B C	4	Side Back 2x	B	20	Belt Carriers 1x
A B C	5	Yoke 1x	B	21	Band 1x
A B	6	Upper Sleeve 2x	B C	22	Pocket Piece 4x
A B	7	Undersleeve 2x	C	23	Center Front 2x
A B	8	Front Facing 2x	C	24	Hood 2x
A B	9	Back Facing 1x	C	25	Waistband 1x
A B	10	Undercollar 1x	C	26	Sleeve 2x
A B	11	Top Collar 1x	<b>LINING PIECES</b>		
A B	12	Collarband 2x	A B	27	Center Front 2x
A	13	Cuff 4x	A B	28	Side Front 2x
A	14	Pocket 2x	A B	29	Center Back 1x
A	15	Flap 2x	A B	30	Side Back 2x
A	16	Tab 1x	A B	31	Yoke 1x

### THE CUTTING LAYOUTS ARE ON THE PATTERN SHEET

#### PREPARING PATTERN PIECES

Choose your size according to the Burda measurement chart on the pattern sheet: dresses, blouses, jackets and coats according to your bust measurement, pants and skirts according to your hip measurement. Adjust the pattern pieces, if necessary, by adding or subtracting the number of inches that your measurements differ from the measurements given in the Burda chart.

#### ABC

Cut out the following pattern pieces in the required size from the pattern sheet:

for the COAT view **A** pieces 1 to 16 and 27 to 31,

for the JACKET view **B** pieces 1 to 12, 17 to 22 and 27 to 31,

for the VEST view **C** pieces 2 to 5 and 22 to 26.

#### LENGTHENING OR SHORTENING PATTERN PIECES

Our pattern is calculated for a height of 5 feet, 6 inches (168 cm). If you are taller or shorter, you may adjust the pattern to fit your size at the lines marked "lengthen or shorten here".

➔ Make sure that you adjust all pieces of one model by the same amount at the same lines.

#### How to lengthen and shorten pattern pieces:

Cut the pattern pieces along the marked lines.

To **lengthen**, slide the two halves of the pattern piece as far apart as necessary.

To **shorten**, overlap the two halves of the pattern piece as far as necessary. Even out the side edges. Remark the buttonholes for view **A**.

#### CUTTING OUT

**FOLD (– – –)** means: here is the center of a pattern piece but in no case a cut edge or a seam. The piece should be cut double, with the fold line forming the center line.

Pattern pieces that are outlined with a broken line in the cutting diagrams are to be placed face down on the fabric.

**The cutting diagrams on the pattern sheet show how the pattern pieces should be placed on the fabric.**

#### C Contrasting Fabric (Rib Knit)

Cut pieces 25 and 26 of contrasting fabric.

➔ See cutting diagrams on pattern sheet.

#### ABC

For a single layer of fabric, the pattern pieces are pinned to the right side. For double layers of fabric, the right sides are facing and the pattern pieces are pinned to the wrong side. The pattern pieces that are shown in the cutting diagram extending over the fold of the fabric should be cut last from a single layer of fabric.

#### SEAM AND HEM ALLOWANCES must be added to the pattern pieces:

**AB – 2" (5 cm)** for hem, **ABC – ¾" (1.5 cm)** at all other seams and edges except on piece 20 for view **B** and at front edge of hood for view **C** (seam allowance is already included).

Use BURDA carbon paper to transfer the pattern outlines (seam and hem lines) and all other lines and markings to the wrong side of the fabric pieces according to package instructions.

#### AB

##### INTERFACING

Cut interfacing as illustrated and iron on the wrong side of the fabric pieces. Transfer pattern outlines to the interfacing pieces.

#### LINING

Use pieces 6, 7, 14, 15 and 27 to 31 to cut the lining for view **A**.

Use pieces 6, 7, 17, 18, 22 and 27 to 31 to cut the lining for view **B**.

➔ See cutting diagrams on pattern sheet.

**Seam and hem allowances must be added to the pattern pieces:**  
¾" (1.5 cm) at all seams and edges.

Transfer pattern piece outlines to the lining pieces.

#### SEWING

**When sewing, right sides of fabric should be facing.**

Transfer all pattern lines to the right side of the fabric with basting thread.

#### ABC COAT / JACKET / VEST

We used contrasting thread for topstitching.

#### A Front Panel Seams

① Lay side fronts right sides together with center fronts, Baste front panel seams (seam number 1) and stitch.

Neaten seam allowances together and press onto front. Topstitch seam ¼" (0.7 cm) wide, catching seam allowances.

**ABC** Stitch **back panel seams** likewise (seam number 2) and topstitch, topstitch view **C** again close to edges.

#### BC Front Panel Seams / Zipper Pockets

② Pin pocket pieces right sides together with center fronts so that ends of pocket opening lines meet with markings on center front. Stitch pocket pieces on marked lines. Secure ends of stitching. Clip allowances in corners close to stitching (arrows) and trim as illustrated.

③ Turn pocket pieces to inside, baste and press. Baste edges on zipper and stitch close to edges.

④ Lay side fronts right sides together with center fronts. Stitch panel seams (seam number 1), catching zipper band at pocket opening edges. Clip allowances above and below zipper bands close to stitching (arrows). Press allowances between clippings onto side fronts. Neaten allowances above and below clippings together, press onto center front. Topstitch center fronts ¼" (0.7 cm) wide next to panel seams (4a), also topstitching close to edge for view **C**.

⑤ Work from the inside to pin other two pocket pieces right sides together with the stitched pocket pieces. Stitch edges together and neaten together. Work from right side of fabric to topstitch side front close to zipper, catching inside pocket piece (5a).

#### ABC Yoke

⑥ Baste and stitch yoke right sides together with back (seam number 4) and fronts (seam number 3).

Press seam allowances onto yoke. Topstitch seams ¼" (0.7 cm) wide, also topstitching close to seams for view **C**, catching seam allowances.

#### B Zipper

⑦ Separate zipper. Baste one half face down on front edge of right front so that the zipper teeth lie on the front piece and the zipper band on the seam allowance.

⑧ Fold band for zipper (piece 21) on fold line right side facing in and stitch across ends. Trim allowances, trim corners diagonally.

Turn band, baste edges and press. Stitch other half of zipper face down on open edge of band so that the zipper teeth lie on the band. Turn in top end of zipper band (8a).

⑨ Press allowances and zipper band to inside. Baste band on left front at placement line so that zipper teeth point toward center front. Topstitch band closely round all edges.

#### AB Facings

⑩ Lay front facings right sides together with back facing, stitch narrow edges together (seam number 5).

Press allowances open. Neaten inside edge of facing.

#### Collar / Lapels

⑪ Baste edge of collarband without marking right sides together with undercollar piece (seam number 6) and stitch. Trim allowances, clip curves and press open. Topstitch close to each side of seam. Stitch other collarband to top collar likewise.

⑫ Stitch undercollar to neck edge between markings (seam number 7). Stitch top collar to facing likewise (seam number 8). Trim seam allowances, clip curves and press open. **Illustration shows undercollar.**

⑬ Pin top collar on undercollar, pushing up extra fabric from outer edge. Stitch collar pieces together from joining seam. Do not catch allowances of collar joining seams on fronts and facings. Clip allowance of fronts and facings at marking close to last stitch (arrow).

#### AB

⑭ Lay allowances up. Pin facings on fronts from marking, pushing up extra fabric of lapels from outer edge. Baste edges together (seam number 9). Stitch, catching zipper in at right front edge for view **B**. Trim allowances, also on collar, trimming hem at lower edge just to 1¼" (3 cm) before end of facing, trim corners diagonally. **Illustration shows view A.**

## Pattern 7735

### AB

- 15** Turn collar. Turn facings to inside. Baste edges, press. Roll undercollar and fronts on FOLD LINE. Hold pieces in place with long diagonal basting stitches.
- 16** Pin collar joining seams together and stitch together from the wrong side with small back stitches by hand.  
Stitch **side seams** (seam number 10). Press allowances open.
- 17** Baste **hem** to inside, press. Topstitch lower edge  $1\frac{1}{2}$ " (4 cm) wide, catching hem. Interrupt stitching for view **B** at left half of zipper. Topstitch edges, collar and lapels  $\frac{1}{4}$ " (0.7 cm) wide.

### A Pockets

- 18** Baste and stitch one pocket piece each of top fabric and lining right sides together, leaving about  $1\frac{1}{2}$ " (4 cm) open at upper edge for turning. Trim seam allowances, trim corners diagonally.  
Turn pockets, baste edges. Topstitch close to upper edge, stitching up opening in seam. Baste pockets on fronts at placement lines. Stitch pockets in place  $\frac{1}{4}$ " (0.7 cm) next to edges.
- 19** **Flaps:** Lay one interfaced and one non-interfaced flap piece each right sides together. Baste and stitch edges together as illustrated. Trim allowances.  
Turn flaps. Baste edges, press and topstitch  $\frac{1}{4}$ " (0.7 cm) wide. Trim allowances at open edges to  $\frac{1}{4}$ " (0.7 cm), neaten together.
- 20** Stitch flaps in place right sides together with joining lines. Secure ends of stitching. Press flap down, topstitch joining seam  $\frac{1}{4}$ " (0.7 cm) wide (20a).
- 21** Fold **tab** on fold line right side facing in. Stitch edges together, leaving an opening for turning (arrows). Trim seam allowances, trim corners diagonally.  
Turn tab, baste edges, press. Sew up opening by hand. Topstitch long edges of tab  $\frac{1}{4}$ " (0.7 cm) wide. Pin tab on center back between markings. Sew on **BUTTONS** spaced  $\frac{3}{8}$ " (1.5 cm) from edges, see x-markings for size 6 (32), sewing on tab.

### B Belt Carriers

- 22** Press lengthwise edges of strip for belt carriers to center, then fold in half. Stitch edges together, topstitch close to fold edge. Cut strip into 4 equal pieces for the belt carriers. Neaten ends and turn in. Pin belt carriers on lower edge at front and back panel seams. Then stitch in place close to top and bottom ends (22a).
- 23** **Zipper underlay:** Lay one piece each of top fabric and lining right sides facing. Stitch lower edges together.  
Trim allowance. Turn zipper underlay piece, topstitch close to lower edge and again  $\frac{1}{4}$ " (0.7 cm) wide. Baste open edges together.
- 24** **Cuffs:** Press allowance at narrow edges of cuffs to inside. Baste zipper under edges so that it opens from the bottom up. Stitch zipper in place close to edges and again  $\frac{1}{4}$ " (0.7 cm) wide.  
Press allowance at narrow edges of cuff lining to inside. Stitch cuff lining right sides together with lower edge of cuff. Press cuff lining down.
- 25** Baste zipper underlay piece under zipper so that the folds face up. Baste lining on zipper over zipper underlay.  
Work from the right side to stitch again in line of zipper stitching, catching zipper underlay piece and lining. Topstitch lower edge of cuff. Fold pleat on zipper underlay piece and baste (25a).

### A Cuffs

- 26** Lay interfaced and non-interfaced cuff pieces each right sides facing and stitch together as illustrated. Trim seam allowances, trim corners diagonally.  
Turn cuffs, baste edges and topstitch  $\frac{1}{4}$ " (0.7 cm) wide. Baste front edges on back edge at placement line (26a).

### AB Sleeves

- 27** Lay undersleeve pieces right sides together with upper sleeve pieces. Baste back sleeve seam (seam number 11) and stitch.  
Press allowances onto top sleeves. Topstitch seam  $\frac{1}{4}$ " (0.7 cm) wide.
- 28** To ease sleeve caps, stitch two closely spaced lines of machine basting (longest stitch setting) from ● to ●.  
Fold sleeves lengthwise. Stitch front sleeve seams (seam number 12). Press seam allowances open.
- 29** Stitch cuffs right sides together with lower edges of sleeves (seam number 13). Press allowances onto sleeves. **Illustration shows view A.**

**Setting in sleeves:** To ease sleeve caps, pull bobbin threads slightly.

- 30** Pin sleeve into armhole, right sides facing. When setting in sleeves, 4 points are important for proper fit:  
➔ Match markings 14 on upper sleeve and front. Match marking on undersleeve with side seam. Match marking at sleeve cap with shoulder marking. Distribute fullness evenly between the ● to avoid forming tucks. Baste and stitch sleeve from sleeve side. Trim seam allowances and press toward sleeves.

### LINING

- 31** Fold center back lengthwise, right side facing in. Stitch on marked lines for ease pleat.  
Press pleat to one side.  
Stitch seams on lining pieces, matching same seam numbers. Set in sleeve linings.  
➔ Press allowances at lower edge of lining and sleeve linings to inside.
- 32** Pin right sides together with facing (seam number 20), matching seams. Stitch, beginning and ending about 4" (10 cm) above hem edge. Clip lining at back neck edge.  
Press seam allowances onto lining. Pin lining inside coat with wrong sides facing.
- 33** Push up lower edge of lining, also on sleeves, and sew on at hem and cuff joining seam.  
Fold extra length of lining down. Sew lining on at front facings. Sew facings on at hem.  
Work **BUTTONHOLES** in right front.  
Sew **BUTTONS** on both fronts at x-markings and for view **A** also at front edges of cuffs, sew ends of cuffs together.

**Tie belt:** Stitch belt pieces together to one long strip.

- 34** Fold belt on FOLD LINE right side facing in. Stitch edges together, leaving narrow edge open for the buckle. Turn belt, Topstitch edges  $\frac{1}{4}$ " (0.7 cm) wide. Neaten end.
- 35** Punch a hole for the prong of the buckle about  $1\frac{1}{2}$ " (4 cm) next to neaten end. Lay belt around bar of buckle and sew in place. Attach **EYELETS** on other end of belt as marked.

**C** **Stitch side seams** (seam number 10). Neaten allowances, press open.

- 36** Fold **waistband** on fold line with wrong side facing in, pin open edges together. Stitch waistband on lower edge of vest matching centers and stretching waistband at bit to fit.  
Neaten allowances together, press onto vest. Topstitch close to joining seam.
- 37** **Hood:** Stitch darts, press to center front. Lay pieces right sides together, stitch center seam. Press allowances to one side. Trim underneath layer of allowance, turn in top layer of allowance and stitch close to edge (37a).
- 38** Attach **EYELETS** on front facing as marked. Turn facing to inside, turn in and stitch close to edge. Stitch hood right sides together with neck edge, matching darts with markings on yoke (38a).  
Trim allowances, neaten together and press onto vest. Topstitch close to joining seam. Baste allowances at front edge to inside.

**39** **Shorten zipper for sizes 8 to 14 (34 to 40):** Transfer the length of the front edge onto the zipper band up to hood joining seam. Separate zipper. Sew a thread bar across top end of zipper. If your zipper is made of metal, you can remove the stoppers and reattach to the shortened zipper.  
Baste the zipper **for all sizes** under front edges from hood joining seam so that the zipper teeth remain exposed. Turn top end of zipper under. Stitch zipper close to edge with the zipper foot of your sewing machine and again  $\frac{1}{4}$ " (0.7 cm) wide (39a).

**Sleeves:** Stitch sleeve seams (seam number 22). Neaten hem, turn in and stitch  $\frac{1}{2}$ " (1.2 cm) wide.

**Set in sleeves** as described and illustrated in step 30. Sleeve seams and side seams must match.  
Insert **BAND** into hood casing through eyelets. Knot ends of band.